Mount as Drive using TonidoDrive

REQUIREMENTS:

- 1. You will need a TonidoPro subscription or have a TonidoPlug Hardware device
- 2. TonidoDrive can be used only for Windows

PLEASE NOTE:

- 1. If you are using a TonidoPlug and want to access your files in your LAN, it is more efficient to connect to the USB drive as a network share. See TonidoPlug: Access as a Drive
- 2. For Operating Systems other than Windows, please go to Access Files As Local Drive

Access your Tonido server files like you would access any other files your hard disk on your Windows based PC.

TonidoDrive is fully secure and is built using a robust Windows filesystem driver so you can access your files with confidence.

Please follow the steps below to install and use TonidoDrive:

Install TonidoDrive

Download Tonido Drive from: http://www.tonido.com/app_drive_home.html

Use the following screenshots for reference for Installation:

1) Click on the download TonidoDrive execution file:



2) Installation progress:

🚔 TonidoDrive Beta	
Installing Please wait while TonidoDrive Beta is being installed.	Ţ
Size: 11568 Kb Files: 22 Folders:	
Extract: msvcm90.dll 100% Extract: msvcp90.dll 100% Extract: clientca.pem 100% Extract: clientcert.pem 100% Created uninstaller: C: \Users\manoj\AppData\Roaming\TonidoDrive\uninst Create folder: C: \Users\manoj\AppData\Roaming\Microsoft\Windows\Start Create shortcut: C: \Users\manoj\AppData\Roaming\Microsoft\Windows\Start Create shortcut: C: \Users\manoj\AppData\Roaming\Microsoft\Windows\Start Starting CBFS Driver install	all.exe t Menu\Pro art Menu\ Cancel

3) Reboot after installation:

📥 TonidoDrive Beta	
	Completing the TonidoDrive Beta Setup Wizard Your computer must be restarted in order to complete the installation of TonidoDrive Beta. Do you want to reboot now?
	 Reboot now I want to manually reboot later
	< Back Finish Cancel

Settings for Map as Local Drive in Tonido

To map your Tonido server, simply enter your Tonido account information, for example:

1) Entering Tonido account information:

URL: http://john.tonidoid.com/

User: john

Password: <Tonido account password>

ſ	TonidoDrive	×
	TonidoDrive Settings	
	Tonido Server URL:	http://john.tonidoid.com
	Account:	john
1	Password:	•••••
•	Remote Answer (optional):	
	Mount Point:	H
		Cancel
	UK	Cancel

2) When you have proper Tonido credentials entered, click Ok:

TonidoDrive	×			
TonidoDrive Settings				
Tonido Server URL:	http://john.tonidoid.com			
Account:	john			
Mounting TonidoDrive : john				
Mount Point:	H:			
Ok	Cancel			

3) TonidoDrive automatically picks up a available mount point. For example, in the above screenshot, TonidoDrive picked "H:" to be the mount point.



4) Now you have your Tonido server mapped as a drive using TonidoDrive. You can add/delete/edit files that is on your Tonido server.

When using Port Forwarding

If you are using port forwarding, please make sure to provide the correct port number